
## TRIANGULAR BOUND BUTTONHOLES

**DETERMINE "BUTTONHOLE LENGTH":** 

BUTTON DIAMETER + BUTTON THICKNESS + 1/8" TO 1/4" FOR EASE = BUTTONHOLE LENGTH




**DETERMINE BASE WIDTH** 


**DRAW BUTTONHOLE ON PAPER** 

 $\Leftarrow$ 

CUT OPEN AND TEST FIT BUTTON



FUSE INTERFACING TO WRONG SIDE OF GARMENT




MACHINE BASTE CENTER PLACEMENT LINE AND END LINES

ADD TWO ROWS OF STITCHING PARALLEL TO PLACEMENT LINE TO INDICATE WIDTH OF BASE

 $\Leftarrow$ 

USE CHALK, PENCIL, OR MARKER TO DRAW TRIANGLE FOR BUTTONHOLE



**CHOOSE BUTTONHOLE FABRIC "PATCH"** 

ULTRASUEDE "FACILE" OR "LIGHT" WORKS WELL WITH HANDWOVENS


FOR EACH BUTTONHOLE, CUT A "PATCH" ON THE STRAIGHT GRAIN 2 " LONGER THAN BUTTONHOLE LENGTH AND 4 TIMES THE BASE WIDTH


 $\Leftarrow$ 

MARK "PATCH" CENTER AND ENDS WITH CHALK

WITH <u>RIGHT</u> SIDES TOGETHER CENTER A "PATCH" OVER MACHINE BASTED MARKINGS ON GARMENT MATCHING CENTERS AND ENDS

MACHINE BASTE ALONG CENTER PLACEMENT LINE BEGINNING AND ENDING WELL BEYOND END LINES






FROM THE WRONG SIDE OF GARMENT (INTERFACING SIDE UP) STITCH EXACTLY IN THE MARKED TRIANGLE USING SMALL STITCHES (20/INCH)

BEGIN AND END ON A LONG EDGE, PIVOTING WITH A TINY DIAGONAL STITCH ACROSS ENDS

**REMOVE CENTER LINE BASTING** 



SLASH BUTTONHOLE "PATCH" FROM OUTER EDGE TO EACH POINT OF STITCHED TRIANGLE

THEN SLASH GARMENT AND "PATCH" ALONG CENTER LINE STOPPING ¼" FROM BASE


 $\Leftarrow$ 


**CLIP TO EACH CORNER OF BASE** 

TURN BASE OF PATCH TO WRONG SIDE AND PRESS

 $\Rightarrow$ 

PRESS EACH REMAINING SECTION OF "PATCH" TOWARD SLIT






NOW TURN REMAINING SECTIONS OF "PATCH" TO WRONG SIDE OF GARMENT, WRAPPING AROUND TRIANGULAR SEAM ALLOWANCES CREATED BY SLASH

 $\Leftarrow$ 

THIS CREATES THE BUTTONHOLE "LIPS"



PRESS FROM THE RIGHT SIDE MAKING SURE LIPS ARE EVEN

FROM RIGHT SIDE STITCH IN DITCH BEGINNING AT BASE CORNER AND ENDING AT POINT ON EACH SIDE


**=** 

TO SECURE BASE, FOLD GARMENT BACK ON ITSELF AND STITCH THROUGH ALL LAYERS OF BASE JUST INSIDE PREVIOUS STITCHING

 $\Rightarrow$ 

TRIM AWAY EXCESS PATCH

**REMOVE ALL BASTING THREAD** 



©2006 Daryl Lancaster